# **Esp-Terminal Commands Documentation**

September 29, 2025

### **Overview**

Commands are case-sensitive and must match exactly, including spaces where specified. Responses are sent via UART, indicating success or failure. Unrecognized commands return "Command Not Found." Commands are grouped by category: System, SD Card, WiFi, HTTP/Network, BLE, and Classic Bluetooth. Each command includes its syntax, purpose, and typical output.

## 1 System Commands

<b>Command Syntax</b>	Description	Output
sysinfo	Retrieves system information (e.g., via a sysinfo function).	System info string (up to 512 bytes).

Table 1: System Commands

### 2 SD Card Commands

These commands require the SD card to be initialized using enable sdcard. File paths are relative to /sdcard/.

<b>Command Syntax</b>	Description	Output
enable sdcard	Initializes the SD card.	"SD card initialized successfully." or "Failed to initialize SD card."
sdcardinfo	Retrieves SD card information (e.g., capacity, type).	SD card info string (up to 512 bytes).
ls	Lists files and directories in the current directory.	File/directory list (up to 1024 bytes).
<pre>mkdir <directory_name></directory_name></pre>	Creates a new directory.	"Directory created." or "Failed to create directory."

<pre><directory_name> empty).</directory_name></pre>	rmdir	Removes the specified directory (must be	"Directory removed."
<pre><directory_name></directory_name></pre>	<directory_name></directory_name>	empty).	
pwd Prints the current working directory path. directory."  Directory path with	cd	Changes the current working directory.	"Directory changed."
pwd Prints the current working directory path. Directory path with	<directory_name></directory_name>		•
			•
newline.	pwd	Prints the current working directory path.	
rm <file_name> Removes the specified file. "File removed." or</file_name>	rm <file_name></file_name>	Removes the specified file.	"File removed." or
"Failed to remove file."			"Failed to remove file."
read Reads the content of the specified file. File content with	read	Reads the content of the specified file.	File content with
<file_name> newline or error</file_name>	<file_name></file_name>		newline or error
message.			message.
write Writes content to the specified file "File written." or	write	Writes content to the specified file	"File written." or
<file_name> (overwrites if exists). "Failed to write file."</file_name>	<file_name></file_name>	(overwrites if exists).	"Failed to write file."
<content></content>	<content></content>		
cp <source/> Copies a file or directory. "Copy successful." or	cp <source/>	Copies a file or directory.	"Copy successful." or
<pre><destination></destination></pre>	<destination></destination>		"Failed to copy."
mv <source/> Moves (renames) a file or directory. "Move successful." or	mv <source/>	Moves (renames) a file or directory.	"Move successful." or
<pre><destination></destination></pre>	<destination></destination>		"Failed to move."

Table 2: SD Card Commands

## 3 WiFi Commands

These commands manage WiFi in STA, AP, APSTA, or NULL modes. Use wifienable mode <mode> first. Some require an active connection in STA or APSTA mode.

<b>Command Syntax</b>	Description	Output
wificonfig	Retrieves WiFi configuration details.	WiFi config string or "Failed to get WiFi config."
wifienable mode <mode></mode>	Enables WiFi in sta, ap, apsta, or null mode.	"WiFi enabled in specified mode." or "Failed to enable WiFi: <error_code>" or "Invalid mode: null, sta, ap, apsta".</error_code>
wifidisconnect	Disconnects from the current WiFi network (STA or APSTA mode).	"Disconnected from WiFi network." or "WiFi not in STA or APSTA mode."
wificonnect <ssid> <password></password></ssid>	Connects to a WiFi access point (STA or APSTA mode).	"Trying to connect to <ssid>. Type wificonnect check for connection status."</ssid>

wificonnect check	Checks WiFi connection status (STA or APSTA mode).	Connection status or "Not connected to any WiFi." or "WiFi not in
wificreate <ssid> <password> <channel></channel></password></ssid>	Creates a WiFi access point (AP or APSTA mode).	STA or APSTA mode." "Creating AP <ssid> on channel <channel>. Type wificreate check for status."</channel></ssid>
wificreate check	Retrieves access point status.	AP status string or "Failed to get AP status."
wificreate disable	Disables the access point (AP or APSTA mode).	"AP disabled." or "WiFi not in AP or APSTA mode."
wifiscan or wifiscan update	Scans WiFi networks and saves to /sdcard/wifi_scan_output.txt (STA or APSTA mode).	"Scan completed, results saved to /sd- card/wifi_scan_output.txt" or "Scan failed: <error_code>" or "WiFi not in STA or APSTA mode."</error_code>
wifiscan result	Reads WiFi scan results from /sdcard/wifi_scan_output.txt.	Scan results with newline or error message.
wifipktcap	Captures WiFi packets (beacon,	"Capture completed,
<type></type>	probe, auth, or deauth) for	saved to file." or
<seconds></seconds>	seconds and saves to filename.	"Capture failed:
<filename></filename>		<error_code>".</error_code>

Table 3: WiFi Commands

## 4 HTTP/Network Commands

These require WiFi in STA or APSTA mode with an active connection. Files are saved to /sdcard/.

<b>Command Syntax</b>	Description	Output
get <url> <file></file></url>	Performs HTTP GET request and saves response to file.	"GET request successful, response saved to file." or "GET request failed: <error_code>" or "WiFi not connected in STA or APSTA mode."</error_code>

<pre>post <url> "<post_data>" <file></file></post_data></url></pre>	Performs HTTP POST with quoted post_data and saves response to file.	"POST request successful, response saved to file." or "POST request failed: <error_code>" or "WiFi not connected in STA or APSTA mode." or "Invalid command format."</error_code>
<pre>upload <url> <file> [content_type] [timeout_ms] [response_file]</file></url></pre>	Uploads file to url via HTTP POST.  Optional: content_type (default: application/octet-stream), timeout_ms (default: 10000), response_file. URL must start with http://orhttps://.	"File upload successful." or "File upload failed: <error_code>. Check URL, file, or network." or validation errors.</error_code>
<pre>download <url> <file></file></url></pre>	Downloads content from url via HTTP GET and saves to file.	"Download successful, file saved." or "Download failed: <error_code>" or "WiFi not connected in STA or APSTA mode."</error_code>

Table 4: HTTP/Network Commands

# 5 BLE (Bluetooth Low Energy) Commands

<b>Command Syntax</b>	Description	Output
bleenable	Enables BLE functionality.	"BLE enabled successfully." or "Failed to enable BLE."
bleconfig	Retrieves BLE configuration details.	BLE config string (up to 128 bytes).
blescan	Scans for BLE devices and saves results	Success message or
<filename.txt></filename.txt>	to filename.txt on SD card.	error message.
bleadvstart	Starts BLE advertising with custom	"BLE advertising
<data></data>	data.	started." or "Failed to
		start BLE advertising."
bleadvstop	Stops BLE advertising.	"BLE advertising stopped." or "Failed to stop BLE advertising."

Table 5: BLE Commands

## **6 Classic Bluetooth Commands**

<b>Command Syntax</b>	Description	Output
blueenable	Enables Classic Bluetooth functionality.	"Classic Bluetooth enabled successfully." or "Failed to enable Classic Bluetooth."
blueconfig	Retrieves Classic Bluetooth configuration details.	BT config string (up to 128 bytes).
bluescan	Scans for Classic Bluetooth devices and	Success message or
<filename.txt></filename.txt>	saves to filename.txt.	error message.
<pre>blueconnect <mac_address></mac_address></pre>	Connects to a Bluetooth device with mac_address.	Connection status message or error message.
bluedisconnect	Disconnects from the current Bluetooth connection.	Disconnection status message or error message.
bluecreate	Creates a Bluetooth server with Name	Server creation status
<name> [PIN]</name>	and optional PIN.	message or error message.
bluecreate disable	Disables the Bluetooth server.	Server disable status message or error message.
bluesend <data></data>	Sends data over the active Bluetooth connection.	Send status message or error message.
<pre>bluesendnc <mac_address> <data></data></mac_address></pre>	Sends data to mac_address (non-connected mode).	Send status message or error message or "No data provided."
bluesendfile	Sends content of filename.txt over	Send status message or
<filename.txt></filename.txt>	Bluetooth.	error message.
bluesendfilenc	Sends filename.txt to	Send status message or
<mac_address> <filename.txt></filename.txt></mac_address>	mac_address (non-connected mode).	error message or "No filename provided."

Table 6: Classic Bluetooth Commands